



Motorola Droid IMAP Instructions

1. From the home screen, touch the **Applications tab** (located on the bottom of the screen).



2. Choose **Email**.




3. Enter your AKO *email address* and *password*.



4. Touch **Manual setup**.




5. Touch **IMAP account**.




6. Enter the *incoming server settings*.


1. Username
2. Password
3. IMAP server:
imap.us.army.mil
4. Port number : 993



7. Touch the **Security type** dropdown.



8. Touch the *security type* dropdown menu. Choose SSL (Accept all certificates)



9. Leave the *IMAP path prefix* box blank.

Incoming server settings

Username
testrobotmail1@your.isp.thx

Password
.....

IMAP server
imap.mail.com

Port
143

Security type
None

IMAP path prefix
Optional

Next

10. Touch **Next**.

Incoming server settings

Username
your.email@us.army.mil

Password
.....

IMAP server
imap.us.army.mil

Port
993

Security type
SSL (accept all certificates)

IMAP path prefix
Optional

Next

11. Enter the *Outgoing SMTP settings*.

1. SMTP server:
mailrouter.us.army.mil
2. Port: 465

Outgoing server settings

SMTP server

mailrouter.us.army.mil

Port

465

Security type

None

Require sign-in.

Username

Password

Next

12. Touch the **Security type** dropdown.

Outgoing server settings

SMTP server

smtp.mail.com

Port

999

Security type

SSL (accept all certificates)


Require sign-in.

Username

Password

Next

13. Touch the desired *security type*.
Choose SSL (Accept all certificates)



14. Ensure **Require sign-in** is selected.



15. Enter the *SMTP information*.

1. Username
2. Password

Outgoing server settings

SMTP server

Port

Security type

Require sign-in.

Username

your.email@us.army.mil

Password

.....

Next

16. Touch **Next**.

Outgoing server settings

SMTP server

mailrouter.us.army.mil

Port

465

Security type

Require sign-in.

Username


your.email@us.army.mil

Password


.....

Next


17. Touch the **Email checking frequency** dropdown and select your desired option.



18. You may select the following *account options* as desired.



19. Touch **Next**.



20. Enter a desired *account name* and the *outgoing message name* then touch **Done**.

